NIST2Stout


1. Setting up files:


1.1. NIST Levels File:

Go to the NIST Atomic Spectral Database.

Click "Levels"

Input the spectrum you are looking for and set the parameters as shown to the right.





The results columns should look like this:

Higlight the levels you want to include and copy them to the clipboard.

Co XI 18 Levels Found Z = 27, CI isoelectronic sequence

Configuration	Term	J	Level
3s2.3p5	 2P*	1 3/2 1	0 1
•		1/2	19345
2- 2-6	 2s	 1/2	313630
3s.3p6	25 	1/2 	313630
3s2.3p4.(1D).3d	2S	1/2	582510
3s2.3p4.(3P).3d	 2P	 3/2	606420 I
382.3p4.(3P).3d	25	1 1/2 1	613480
	i	i	i
3s2.3p4.(3P).3d	2D	5/2	615140
		3/2	631680
3s2.3p4.(3P).4s	 4P	5/2	1181100
	I	3/2	1189920
3s2.3p4.(3P).4s	 2P	 3/2	1202070
332.3p4. (3E).43	25	1/2	1211780
	ĺ	i i	İ
3s2.3p4.(1D).4s	2D	5/2	1226890
	l	3/2	1227710
3s2.3p4.(3P).4d	2D	5/2	1471200
		i i	i
3s2.3p4.(1D).4d	2D	5/2	1510800
	 	3/2	1523400
		i i	i
Co XII (3p4 3P<2>)	Limit		[2462610(1900)]
Query time: 0.4 sec			

Co XI	18 Levels Found
Z = 27, 0	I isoelectronic sequence


onfiguration 	Term	J 	Level
		0.40	
		3/2 1/2	0 19345
		i i	
	2S	1/2 	313630 I
s2.3p4.(1D).3d		1/2	582510
s2.3p4.(3P).3d	 2P	l I 3/2	 606420
sz.sp4.(se).su	25	1/2	613480
		i i	
s2.3p4.(3P).3d		5/2	615140
		3/2	631680
s2.3p4.(3P).4s	4P	5/2	1181100
			1189920
s2.3p4.(3P).4s	 2P	l 3/2	 1202070
sz.sp4.(sr).4s	1 22	1 1/2	
		1 2/2	1211700
s2.3p4.(1D).4s			1226890
		3/2	1227710
s2.3p4.(3P).4d	I I 2D	l 5/2	1471200
			1771200
s2.3p4.(1D).4d		5/2	
		3/2	1523400
o XII (3p4 3P<2>)	Limit		[2462610(1900)]

Paste the contents into an empty text file. The name of the file should be X.NIST.txt, where X is whatever you want the base output name to be.

test.	est.bd. 🖸				
1	3s2.3p5 · · · · · · · 2P* · · · · 3/2 · · · · · · · · · · · · · · · ·				
2	19345				
3					
4	3s.3p6				
5					
6	3s2.3p4.(1D).3d···· ·25····· ·1/2· ········582510····				
7					
8	3s2.3p4.(3P).3d 2P 3/2 606420				
9	1/2 613480				
10					
11	3s2.3p4.(3P).3d 2D 5/2 615140				
12	3/2 631680				
13					
14	3s2.3p4.(3P).4s··· 4P···· 5/2 · · · · · · · 1181100 · · · ·				
15	3/2				
16					
17	3s2.3p4.(3P).4s··· ·2P···· ·3/2· ······1202070····				
18					
19					
20	3s2.3p4.(1D).4s 2D 5/2 1226890				
21	3/2 1227710				
22					
23	3s2.3p4.(3P).4d 2D 5/2 1471200				
24					
25	3s2.3p4.(1D).4d 2D 5/2 1510800				
26					

1.2 NIST Lines File:


Go to the Lines section of the NIST Atomic Spectral Database



Enter the spectrum to match the levels file and edit the following parameters



Continue to edit parameters on the Line form



Select the lines and copy them to the clipboard.

If you did not find the data you need, please inform the ASD Team.

CO AL 9 LINES OF Data FOUND

Z = 27, CI isoelectronic sequence

Paste the line data to a blank text file. Name the text file X.tp.NIST.txt where X is the same base name used for the level file.

2. Running the script:

The program has 2 parts, nist2stout.py and n2sWrapper.py. The program can be run for one species with nist2stout.py or in a batch mode with n2sWrapper.py.

2.1 Running for a Single Species:

Running the program for a single species has a simple syntax. From the command line enter nist2stout.py <name of level file> <name of line file>. The code will run and you will end up with X.nrg.txt and X.tp.txt.

2.2 Running as a Batch:

Consider this directory structure:

```
<Base>
<Ar>
ar_2.nist.txt
ar_2.tp.nist.txt
<Be>
be_3.nist.txt
be_3.tp.nist.txt
be_4.nist.txt
bet 4.tp.nist.txt
```

You can automatically run NIST2Stout on all of these species by copying nist2stout.py and n2sWrapper.py to the Base directory. Then execute n2sWrapper.py with no other parameters. The code will go through all subdirectories looking for matching pairs of level files (X.nist.txt) and line files (X.tp.nist.txt). For each pair it finds, it will execute nist2stout.py as in

described in Section 2.1. The Stout formatted files should end up in the same directories as the NIST source files for that species.

3. Gotchas and Troubleshooting:

- Make sure that all of the levels necessary to reference the transitions in the lines file (X.tp.nist.txt) are included in the levels file (X.nist.txt).
- Make sure that you have all of the necessary columns (and no others) included in the levels and lines files.